

Installing DiCentra on Windows 7

DiCentra will run correctly on Windows 7; however it needs *Microsoft's .NET 1.1 Framework* installed to do so. When you do this, Windows 7 reports an incompatibility. This should be ignored. Detailed instructions are given below.

.NET 1.1 will co-exist with newer versions of .NET on your machine, but DiCentra must have .NET 1.1 available for it to work.

Installing from the Web

You will need to download .NET 1.1 from the Microsoft web site and DiCentra from the Wilbur Imaging web site. Your licence image, licence user name and key will have been provided by e-mail.

Downloading components:

1. Go to the *DiCentra* web page at:
www.wilburimaging.com/dicentra
2. Click on the [Download the software](#) link near the top of the page or scroll down to about 2/3 the way down.
3. Click on the Download button for the [DiCentra Application](#) and save it to a convenient place. ([DiCentra 3.x.xx.zip](#))
4. Click on the Download button for the [Microsoft .NET 1.1 Framework](#) and save it to a convenient place. The file will probably be called [dotnetfx.exe](#).
5. Your licence key image will have been emailed as a zipped attachment. [Save](#) the attachment and then [unzip](#) it to extract the licence image.

Installing .NET 1.1:

6. [Double-click](#) on [dotnetfx.exe](#).
7. It may take a while before anything happens, and then you will be asked if you want this file to make changes to your computer. Click on [Yes](#)
8. When it asks if you would like to install *.NET Framework 1.1 Package*, click on [Yes](#).
9. You will then be told that this package has known compatibility issues. Click on [Run Program](#).
10. When asked, [Agree](#) to the licence terms. Eventually you will be told that installation of .NET 1.1 is complete.

Installing DiCentra:

11. Right-click on [DiCentra 3.x.xx.zip](#) and select [Extract All](#) to create a folder called [DiCentra 3.x.xx](#).
12. Inside this folder you will see two files called [Setup](#). [Double-click](#) on the one with a computer as an icon – not the one with a gear wheel. (Alternatively, if your machine shows the file extensions [double-click](#) on [Setup.exe](#).)
13. When it asks if you would like to install this application from an unknown publisher, click [Yes](#).

14. Work through the installation wizard by clicking on [Next](#) and [Agree to the licence](#) as necessary.

Installing your licence:

15. [Double-click](#) on the *DiCentra* icon on your desktop to start the application.
16. [Dismiss](#) the welcome message and then click on [Help > Install Licence](#)
17. [Copy and paste](#) your user name and key from the e-mail message into the boxes provided and [click OK](#)
18. You will be informed that the title screen image needs to be installed. [Click OK](#).
19. When the file browser dialogue appears navigate to the [Licence Image](#) that you unzipped earlier. It will have your club name as its title. [Click Open](#).
20. After a few seconds you should be informed that the licence has been installed.
21. *DiCentra* is now ready to use.

Installing from CD

Your *DiCentra* CD contains everything you need to install DiCentra, except your licence key user name and key. These will have been provided to you by e-mail or on paper.

22. [Open the CD](#) on your computer. You will see some folders and files listed.
23. **Installing .NET 1.1:**
24. [Double-click](#) on the file called [dotnetfx](#).
25. It may take a while before anything happens, and then you will be asked if you want this file to make changes to your computer. Click on [Yes](#)
26. When it asks if you would like to install *.NET Framework 1.1 Package*, click on [Yes](#).
27. You will then be told that this package has known compatibility issues. Click on [Run Program](#).
28. When asked, [Agree](#) to the licence terms. Eventually you will be told that installation of .NET 1.1 is complete.
29. **Installing DiCentra:**
30. Go back to the CD listing and you will see two files called Setup. [Double-click on the first one](#) (it should have a computer as an icon – not the one with a gear wheel).
31. When it asks if you would like to install this application from an unknown publisher, click [Yes](#).
32. Work through the installation wizard by clicking on [Next](#) and [Agree to the licence](#) as necessary.
33. **Installing your licence:**
34. [Double-click](#) on the *DiCentra* icon on your desktop to start it up.
35. [Dismiss](#) the welcome message and then click on [Help > Install Licence](#)

36. Either *type in* your user name and key exactly as they appear on the printed sheet, or *copy and paste* them from the e-mail message into the boxes provided and *click OK*.
37. You will be informed that the title screen image needs to be installed. *Click OK*.
38. When the file browser dialogue appears navigate to the *Licence Image* folder on the CD and select the image. It will have your club name as its title. *Click Open*.
39. After a few seconds you should be informed that the licence has been installed.

40. *DiCentra* is now ready to use.

Steve Wilbur
9/5/11
software@wilburimaging.com